

# Guide for AG-CX350 clip import from SD card on (Mac) Adobe Premiere Pro CC Ver.13.0

The screenshot shows the Adobe Premiere Pro interface. The Media Browser window is open, displaying a list of storage locations. The 'Panasonic P2' option is checked with a white checkmark. A blue callout box with a white border points to the 'Panasonic P2' entry, containing the text: '② Click Directory viewers button. ※Panasonic P2 is checked.' Another blue callout box with a white border points to the 'Media Browser' button in the top-left corner of the Media Browser window, containing the text: '① Select SD card from Media Browser window.'

② Click Directory viewers button.  
※Panasonic P2 is checked.

① Select SD card from Media Browser window.

# Guide for AG-CX350 clip import from SD card on (Mac) Adobe Premiere Pro CC Ver.13.0

The screenshot shows the Adobe Premiere Pro interface. The Media Browser panel is open, displaying a list of folders. The 'A004' folder is selected in the sidebar, and its contents are shown in the main panel. The 'File Directory' option is highlighted in the list. A blue callout box with the text '③ Select the File Directory.' points to the 'File Directory' option. Another blue callout box with the text 'Folders are displayed.' points to the 'A004' folder in the sidebar.

Media Browser

Local Drives

- A004
  - CONTENTS
  - DCIM
  - private

File Directory

Panasonic P2

Premiere Pro Project

RED

Sony HDV

Team Project Assets

XDCAM-EX

XDCAM-HD

Drop media here to create sequence.

③ Select the File Directory.

Folders are displayed.

# Guide for AG-CX350 clip import from SD card on (Mac) Adobe Premiere Pro CC Ver.13.0

The screenshot displays the Adobe Premiere Pro interface. The Media Browser on the left shows a folder hierarchy: A004 > PANA\_GRP > 001RCQA. A file named 'A004C001\_190404\_B90G.MOV' is selected and highlighted with a white box. A blue callout bubble points to this file with the text: '④ Select "PANA\_GRP" folder of MOV files, or "AVCHD" folder of AVCHD files. ⑤ Open hierarchy of folders to displays MOV files or MTS files.' The Program Monitor on the right shows a video clip of a person sitting on a chair in a studio setting. A blue callout bubble points to the clip with the text: '⑥ Right-click on clips and select "Import"'. The timeline at the bottom shows a single clip on the track.

⑥ Right-click on clips and select "Import"

④ Select "PANA\_GRP" folder of MOV files, or "AVCHD" folder of AVCHD files.  
⑤ Open hierarchy of folders to displays MOV files or MTS files.